

Logout

Web Port Close

## SIP Settings [Line 1]

### VoIP

SIP Settings

- Line 1

VoIP Settings

- Line 1

### Basic

Phone Number	<input type="text" value="+6624025010"/>
Registrar Server Address	<input type="text" value="catnextgen.com"/>
Registrar Server Port	<input type="text" value="5060"/> [1-65535]
Proxy Server Address	<input type="text"/>
Proxy Server Port	<input type="text" value="5060"/> [1-65535]
Presence Server Address	<input type="text"/>
Presence Server Port	<input type="text" value="5060"/> [1-65535]
Outbound Proxy Server Address	<input type="text" value="202.129.61.102"/>
Outbound Proxy Server Port	<input type="text" value="5165"/> [1-65535]
Service Domain	<input type="text" value="catnextgen.com"/>
Authentication ID	<input type="text" value="6624025010@catnextgen.com"/>
Authentication Password	<input type="password" value="....."/>

**VoIP Settings [Line 1]**

Logout

Web Port Close

VoIP

SIP Settings

- Line 1

VoIP Settings

- Line 1

**Basic**

G.722	Enable	<input type="radio"/> Yes <input checked="" type="radio"/> No
	Priority	1 [1-255]
PCMA	Enable	<input checked="" type="radio"/> Yes <input type="radio"/> No
	Priority	2 [1-255]
G.729A	Enable	<input checked="" type="radio"/> Yes <input type="radio"/> No
	Priority	1 [1-255]
PCMU	Enable	<input type="radio"/> Yes <input checked="" type="radio"/> No
	Priority	1 [1-255]
DTMF Type		<input checked="" type="radio"/> RFC2833 <input type="radio"/> Inband <input type="radio"/> SIP INFO

**Advanced**

RTP Packet QoS (DSCP)	0 [0-63]
RTCP Packet QoS (DSCP)	0 [0-63]
Enable RTCP	<input type="radio"/> Yes <input checked="" type="radio"/> No
Enable RTCP-XR	<input type="radio"/> Yes <input checked="" type="radio"/> No
RTCP&RTCP-XR Interval	5 seconds [5-65535]
SRTP Mode	RTP/SRTP
Enable Mixed SRTP&RTP by Conference	<input checked="" type="radio"/> Yes <input type="radio"/> No
Enable Mixed SRTP&RTP by Transfer	<input checked="" type="radio"/> Yes <input type="radio"/> No

Save

Cancel